

# set\_tracking.php

Sets the locating interval, at ignition on for a vehicle. Switches hardware specific the travel interval, time interval or course change.

## Description

POST

`set_tracking.php?company=COMPANY_RTIKEY&vehicle=VEHICLE_RTIKEY&mode=intelligentlocating&value=active`

## Parameter

Parameter	Description	Type	Note	Mandatory
company	RTI company key	string		yes
vehicle	RTI vehicle key	string		yes
mode	which type of locating interval should be set	string	<ul style="list-style-type: none"><li>coursechange</li><li>distanceinterval</li><li>minuteinterval</li><li>intelligentlocating</li></ul>	yes
value	Value of the selected interval	int/string	see "Possible values"	yes

## Possible values

Parameter	Description	Type	Possible values
coursechange	Locate at ignition on at course change	int	<ul style="list-style-type: none"><li>0 = off</li><li>1 = on</li></ul>
distanceinterval	Locate with ignition on for all X km	int	<ul style="list-style-type: none"><li>0 = Kilometer tracking deactivated</li><li>1 = Locate every km</li><li>2 = Locate every 2 km</li><li>5 = Locate every 5 km</li><li>10 = Locate every 10 km</li></ul>
minuteinterval	Locate with ignition on for all X min	int	<ul style="list-style-type: none"><li>0 = Time interval disabled</li><li>1 = Locate every 1 minutes</li><li>2 = Locate every 2 minutes</li><li>5 = Locate every 5 minutes</li><li>10 = Locate every 10 minutes</li><li>15 = Locate every 15 minutes</li><li>30 = Locate every 30 minutes</li></ul>
intelligentlocating	when all 3 locating intervals are activated	string	<ul style="list-style-type: none"><li>inactive</li><li>active</li></ul>

## Return

By default, a **CSV string** is returned, which contains **OK** for each vehicle on success. If an error occurs, an **"ERROR:Description"** is returned.

## Example calls

sets the locating interval to 5 km

```
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle=VEHICLE_RTIKEY&mode=distanceinterval&value=5
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle={"type":"car_ident","groupKey":"GROUP_RTIKEY","ident":"VEHICLE_IDENT"}&mode=distanceinterval&value=5
```

#### **sets the locating interval to 2 minutes**

```
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle=VEHICLE_RTIKEY&mode=minuteinterval&value=2  
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle={"type":"car_ident","groupKey":"GROUP_RTIKEY","ident":"  
VEHICLE_IDENT"}&mode=minuteinterval&value=2
```

#### **activates the change of course**

```
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle=VEHICLE_RTIKEY&mode=coursechange&value=1  
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle={"type":"car_ident","groupKey":"GROUP_RTIKEY","ident":"  
VEHICLE_IDENT"}&mode=coursechange&value=1
```

#### **activates the intelligent tracking**

```
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle=VEHICLE_RTIKEY&mode=intelligentlocating&value=active  
https://map.yellowfox.de/rti/set_tracking.php?company=COMPANY_RTIKEY&vehicle={"type":"car_ident","groupKey":"GROUP_RTIKEY","ident":"  
VEHICLE_IDENT"}&mode=intelligentlocating&value=active
```